

type	1	2	7	12	13	14	15	16	17	18	19	20	21	23	24	25	27	31	32	33	34	45	67	68	type label
ident	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	1 Washing Machine
type	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	2 Tumble Dryer
deviceName	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	7 Dishwasher
deviceIdentLabel	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	12 Oven
xkmIdentLabel	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	13 Oven Microwave
type																									14 Hob Highlight
state	1	2	7	12	13	14	15	16	17	18	19	20	21	23	24	25	27	31	32	33	34	45	67	68	15 Steam Oven
ProgramID	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	16 Microwave
status	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	17 Coffee System
programType	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	18 Hood
programPhase	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	19 Fridge
remainingTime	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	20 Freezer
startTime	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	21 Fridge /Freezer
targetTemperature				x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	23 Robot Vacuum Cleaner
temperature				x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	24 Washer Dryer
signalInfo	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	25 Dish Warmer
signalFailure	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	27 Hob Induction
signalDoor				x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	31 Steam Oven Combi
remoteEnable	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	32 Wine Cabinet
light				x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	33 Wine Conditioning Unit
elapsedTime	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	34 Wine Storage Conditioning Unit
spinningSpeed	x																								45 Steam Oven Micro
dryingStep		x																							67 Dialogoven
ventilationStep										x															68 Wine Cabinet / Freezer
plateStep						x												x							
ecoFeedback	x	x	x																						
batteryLevel																									
type	1	2	7	12	13	14	15	16	17	18	19	20	21	23	24	25	27	31	32	33	34	45	67	68	
actions*	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	
processAction**																									
START	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	
STOP	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	
PAUSE																									
START SUPERFREEZING												x	x												x
STOP SUPERFREEZING												x	x												x
START SUPERCOOLING												x	x												
STOP SUPERCOOLING												x	x												
light				x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	
startTime	x	x	x																						
ventilationStep										x															
programId														x		x									
targetTemperature											x	x	x						x	x	x				x
deviceName	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	
powerOn	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	
powerOff	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	
colors										x															
modes											x	x	x												x
type	1	2	7	12	13	14	15	16	17	18	19	20	21	23	24	25	27	31	32	33	34	45	67	68	
programs	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	

* due to appliance limitations not all "actions" are supported from elder appliance generations. Availability can be checked by a "GET actions" request.
 ** due to appliance limitations not every "processAction" feature is supported by every appliance. Availability can be checked by a "GET actions" request.